N 64 288 36

(ACCESSION NUMBER)

(PAGES!

(NASA CR OR TMX OR AD NUMBER)

OTS PRICE

XEROX \$ ____

MICROFILM \$ _____

COMPLETE SERVICE OF MEET

COLLEGE PARK, MÄRYLAND

Technical Report TR64-10 August 1964

.NsG-398

Pattern Recognition: II. RAMP and REST

Two Image Analysis Programs

by

James N. Orton Azriel Rosenfeld

The computer programs described in this report were written under the supervision of Dr. Azriel Rosenfeld, Research Associate Professor (P.T.) at the Computer Science Center. Programming personnel were Messrs. James N. Orton, Ernest W. Smith and Bernard Altschuler of the Budd Information Sciences Center, McLean, Virginia. Their time was supported by Contract NAS5-3461 between The Budd Company and the National Aeronautics and Space Administration. The computer time used was supported almost entirely by the National Aeronautics and Space Administration under Grant NSG-398 to the University of Maryland.

ABSTRACT

This report presents detailed descriptions of two basic computer programs for the analysis of the connectivities and shapes of regions in digitized images. The application of these programs to the analysis of TIROS cloud cover pictures and outline maps made from such pictures is also briefly described.

The programs are written in FAP. They have been extensively tested on the 7090.

CONTENTS

Section		
1.	Introduction	1
2.	RAMP: Region Area Measurement Program	4
	2.1 General description	4
	2.2 Input	6
	2.3 Operating parameters	7
	2.4 Logical description	8
3.	REST: Region-Enclosed Square Tabulator	11
	3.1 General description	11
	3.2 Input	12
	3.3 Operating parameters	12
	3.4 Logical description	13
4.	Application to TIROS pictures and nephanalyses	16
	4.1 TIROS pictures	16
	4.2 Nephanalyses	19

LIST OF FIGURES

		Following Page
1.	Typical TIROS Cloud Picture	4
2.	Typical Cloud Cover Maps	4
3.	RAMP Printout for a Typical Map	5
4.	List of Regions in Figure 3	5
5.	RAMP Flow Chart	10
6.	RAMP Symbolic Program Listing	10
7.	Typical Input to REST	12
8.	Output of REST for the Input of Figure 7	12
9.	REST Flow Chart	16
10.	REST Symbolic Program Listing	16
11.	RAMP Outputs for a Typical Cloud Picture Various Threshold Levels	at 19

1. Introduction

Computer programs for processing pictorial information have received some attention in recent years. However, research in this field has tended to be concentrated in specific areas, among them

- (a) Development of algorithms for "local" processing of twodimensional data arrays, with application to "smoothing" or otherwise simplifying given pictorial information (Dimen 1955, Kirsch 1957, Unger 1958, Narasimhan 1964)
- (b) Development of techniques for processing pictures which consist of discrete, well-defined parts in given topological and metric relationships (Freeman 1961, Hodes 1961, Sutherland 1963, Kirsch 1964)

This report describes two computer programs designed as basic tools for analyzing the sizes and shapes of connected regions in an image defined by those image points having a given range of brightness (or density) values. These programs represent one approach to bridging the gap in digital picture processing research between local processing on the one hand and the processing of pictures consisting of discrete parts on the other.

The first of these programs, called the Region Area Measurement Program (RAMP), identifies, computes the area of, and displays connected regions on a given set of digitized pictures input from magnetic tape.

As a by-product it also produces from the line-by-line, element-by-element digital representation of the pictures a condensed representation on magnetic tape in terms of the picture-element intervals belonging to each region on succeeding lines. Each interval is tagged by a number uniquely identifying the region of which it is a part. This tape is thus a reconstructible condensation of the information displayed (printed out) by RAMP. It may be used as input to other image analysis programs, for example the second program described in this report.

The second program, called the Region-Enclosed Square

Tabulator (REST), produces from this interval representation of a picture

a frequency distribution of the squares of all possible sizes enclosed within

each region. Two square types are distinguished: these which touch a

region boundary ("exterior" squares) and these which do not ("interior"

squares).

RAMP and REST have been developed as general-purpose tools for analyzing the connected regions on any image. RAMP distinguishes the regions and measures their sizes. REST provides basic information about the shapes of the regions; for example, a distribution of squares which falls off abruptly for large square sizes is intuitively indicative of an elongated region.

The next two sections of this report describe in detail the structure and operation of the RAMP and REST programs. The concluding

section discusses the application of both programs to representative

TIROS cloud cover pictures and to outline drawings (nephanalyses) made

from such pictures.

2. RAMP: Region Area Measurement Program

2.1 General description

The principal function of RAMP is to identify and measure the connected regions defined by points having a given range of brightness values on a digitized picture. Two important examples of pictures to which RAMP can be applied are

- (a) Any digitized picture, where the given range of brightness values are those exceeding an arbitrary threshold. An example is the TIROS picture shown in Figure 1, where the brightness threshold may be selected (Arking 1964) so as to discriminate between the cloud and noncloud portions of the picture. (For this threshold, RAMP will analyze the connected masses of cloud cover on the picture.)
- (b) A digitized line drawing consisting of black lines on a uniform white background. For this type of picture and a reasonable choice of brightness threshold, RAMP will analyze the regions enclosed by the lines. An example is the set of twenty-eight cloud cover maps (made from TIROS pictures) shown in Figure 2.

The input to the program is a magnetic tape digital representation of the picture or set of pictures to be analyzed. This tape can be prepared from an original hard copy picture by scanning it as described in the next subsection.






Figure 1
Typical TIROS Cloud Picture








FIGURE 2.
TYPICAL CLOUD COVER MAPS

The program produces three outputs:

- (a) A pictorial printout as illustrated in Figure 3, corresponding to the upper left corner picture in Figure 2, in which each connected region of above-threshold picture elements has been assigned a distinguishing symbol. The set of symbols to be used for this purpose can be specified by the user.

 Up to forty-seven characters can be used. In the printout, each element of a connected region is represented by the character assigned to the region. The below-threshold elements are represented by blanks. The printout is thus a "negative" in the sense that "dark" regions are output as blanks, while "bright" regions are printed out as aggregates of characters.
- (b) A printed list of the connected regions and their areas.*

 Such a list for the picture of Figure 3 is shown in Figure 4.
- (c) A magnetic tape condensation representing the pictures in terms of the intervals in which a set of parallel scan lines intersect each region. These intervals are expressed in the form (a,b), where a and b are the picture element numbers of the leftmost and rightmost elements in the given interval. The elements are numbered left to right from 1 to P, the picture width. (A detailed description of the format of this tape, which is the input to the REST program, is given in Section 3.)

^{*}The area of a region is defined as the number of picture elements it contains.




FIGURE 3 RAMP PRINTOUT FOR A TYPICAL MAP

Region	Region Area
Y	180
1	140
2	4
U	7410
3	597
4	456
5	15
6	694
7	160
Z	1066

Figure 4
LIST OF REGIONS IN FIGURE 3

2.2 Input

The images used as input to RAMP were converted into an IBM-compatible digital tape using a high resolution optical-mechanical scanner currently in operation at the National Bureau of Standards. (The continuing cooperation of Mr. Leonard Cahn of the Bureau in making this scanner available is gratefully acknowledged.) This scanner was made by converting a metal lathe. The image to be scanned is placed on a three inch diameter drum which is inserted in the lathe. At one end of the drum there is a slip ring which can be rotated with respect to the drum. On the slip ring is cemented a photograph of white and black lines and a black space corresponding to clock pulses and an inter-record gap. The rotation of the slip ring with respect to the drum determines the point at which the scanner starts to scan the photograph.

The optical system used in the scanner consists of a light source, a lens, a square aperture (1/192" x 1/192"), and a multiplier phototube. Electrical signals are obtained at the output of the multiplier phototube. A second optical system is placed in front of the slip ring and the output of its multiplier phototube provides clock pulses for the entire electrical system. This second optical system is connected to the automatic feed of the lathe. Rotation of the drum provides the lateral motion across the picture and the automatic feed of the lathe provides the longitudinal motion.

The output of the main multiplier phototube is fed into a video amplifier and amplified. The amplified signal is then fed into a three

bit analog-to-digital converter. The resulting binary signal is then fed into an Ampex digital tape recorder and recorded on magnetic tape at 200 bits per inch.

The scanner is equipped with preselected start and stop limits.

The maximum over-all scanning area is 9 x 10.4 inches. The area is scanned from left to right starting in the upper left hand corner. Each line is equal to one record; its end is marked by an end of record gap. Each record contains

288 words representing 1728 picture elements. The entire scanning area contains approximately 2000 records.

2.3 Operating parameters

RAMP is coded for an IBM 7090 computer in the FAP symbolic assembly language. For input-output a University of Maryland modified version of the FORTRAN I/O Hollerith package was used.

Parameter cards must be supplied for each run to specify the number and size of the pictures in the sequence to be processed. All pictures to be processed during a single run of the program must be stored on a single magnetic tape. Each record on the tape contains information about one picture line; lines are numbered consecutively from 1 to L, where L is the total number of lines stored on the tape.

The parameter cards to be supplied for a set of p pictures are the following:

Symbolic Location and Contents		ents	Parameter Definition	ParameterLimits
ENDR + 0	DEC	R	Picture 1: . number of lines in picture	l to magnetic tape storage limit
+ 1	DEC	w _b	 beginning word of line (6 picture ele- ments per word) 	$1 \le W_b \le W_e$
+ 2	DEC	W _e	. ending word of line	$W_b \le W_e \le 20$
ENDR + 3, 4, 5			Picture 2: same	
ENDR + 3(p-1) + 0, 1, 2			Picture p: same	
ENDR + 3p	DEC	0	Signal for end of picture sequence	

These cards are inserted in the symbolic program deck just prior to the last symbolic card ("END" card).

2.4 Logical description

The input to RAMP is a binary tape containing digitized information from a scanned image. The scanner described in Subsection 2.2 assigns each map element to one of eight gray levels; the program, however, is concerned only with "black" (below threshold) and "white" (above threshold) elements.

One row (= line) of elements is read in at a time. For it, the program records all of the intervals between "black" elements, giving their beginning and ending element numbers. For the first row, these intervals are assigned successive region numbers and a count is started for each region giving the number of elements in the interval. Starting with the second row, all of the intervals for a given row m are compared with the intervals of the previous row m-l in the following manner: If an interval (c, d) of row m overlaps an interval (a, b) of row m-1 (that is, if c is not greater than b + 1 of if d is not less than a - 1) then the interval (c, d) is tagged with the region number of the interval (a, b), and the number of elements in (c, d) is added to the cumulative count of that region. If an interval of row m overlaps two intervals (a₁, b₁) and (a₂, b₂) of row m-1, the cumulative count for the region of the interval (a2, b2) is added to the cumulative/ for the region (a_1,b_1) and the region number of (a_2,b_2) is eliminated, (a_2, b_2) being tagged with the region number of (a_1, b_1) . If an interval (c, d) of row m does not overlap with any interval in row m-l, then it is assigned a new region number. Each time processing for a line is completed, its tagged intervals are written on magnetic tape.

It is necessary to make only one pass over all the rows of the picture tape using this parallel type of processing.* Furthermore, at any given time only one row of elements and the intervals from two rows are in memory, thus minimizing the amount of storage required.

^{*}However, one additional pass over the interval tape is required to complete the numbering of the regions.

For each region the program puts out the coordinates of an identifying element and the total number of elements. The identifying element is the first element to which the program had assigned that region number which it eventually assigns to the entire region after all "overlaps" have been consolidated as described above. If a region has no "overlaps," this is simply the first element of the region encountered by the scan (the upper left element). For a "U" shaped region, the identifying element will be the upper left element of the left arm of the "U", even though the left arm is shorter than the right arm, so that the right arm was encountered first.

The symbols identifying the regions for output are assigned in rotating order A, B, ..., Z, 1, 2, ..., 9, +, -, /, =, ', ..,), \$, *, "comma", (corresponding to the order in which the scan encountered the upper left element of the entire region (rather than the identifying element). However, the regions are <u>listed</u> in the output in order of their identifying elements. This explains the order of listing of the region data in Figure 4, above, and Figure 7, below.

Figures 5 and 6 show a detailed flow chart and the 7090 symbolic assembly (FAP) listing for RAMP.

Figure 5

RAMP Flow Chart




Figure 5 - Sheet l




Figure 5 - Sheet 2







Figure 5 - Sheet 3





DUPLICATES PROCESSING





Determine whether next interval to be compared is current or previous








Figure 5 - Sheet 7




Figure 6

RAMP Symbolic Program Listing

```
REGION AREA MEASUREMENT PROGRAM
                 RAMP
 X1
        CLA
                 BEGW
        SUB
                 ONE
        STO
                 BEGW
        CLA
                 ENDW
        ADD
                 90+2
        STA
                 A1+1
        STA
                 A21+1
        STA
                 P5-1
        STA
                 P5-2
        STA
                 P5+2
        STA
                 Q3 + 3
        STA
                 Q5=3
        STA
                 Q5+6
        STA
                 Q8-2
        CLA
                 ENDW
        SUB
                 BEGW
        STA
                 A0 + 1
        STA
                 P0
        STA
                 Q5 + 3
        LXA
                 ENDR,1
        SXD
                 D3-4,1
 X 0
        CALL
                 RDSBIN
                                 READ BINARY
        TIX
                 0.0.8
        TIX
                 L(IOC),7,0
        TIX
                 0,1,0
        TRA
                 Α0
                                 READ IN ONE RECORD STARTING
L(IOC) IORT
                 GRID,0,-1
                                 IN LOCATION GRID
 ΑO
        AXT
                 0,4
                                      AO THRU A2-1 SEARCHES FOR 1ST WHITE
        AXT
                 **,2
        AXT
                 6,1
        CAL
                 MASK
 A1
        ARS
                 0
        ANA
                 **,2
        LGR
                 33
        RQL
                 1
       LGL
                 2
        CAS
                 THREE
        TRA
                 A 2
                                      TRA IF A WHITE ELEMENT
        NOP
       CLA
                 Al
        ADD
                 SIX
        STO
                 A1
        CLA
                 LFS
        ADD
                ONE
        STO
                 LFS
        CLA
                MASK1
        ANA
                 A1+2
        SUB
                 SIX
        STA
                 A1+2
 A11
        TIX
                 A1-1,1,1
                                      NEXT INST FOR A NEW WORD
       SXA
                 A1,0
                                                      Figure 6 - Sheet 1
```

```
CLA
               TTHREE
      STA
               A1+2
      TIX
               A1-2,2,1
      TRA
               A5A
Α2
      CLA
                                    A2 THRU A5-1 SEARCHES FOR NEXT
               CON4
      STA
               A2-1
                                    BLACK ELEM.
      CLA
               LFS
      STO
               RTS
      CLA
               Αl
      ADD
               SIX
      STA
               A21
      CLA
               MASK1
      ANA
               A1+2
      SUB
               SIX
      STA
               A21+2
      SXA
                                    RESET ROUTINE AT FOR NEXT ROW
               Al,0
      CLA
               TTHREE
      STA
               A1+2
      TNX
                                    TRA FOR NEW WORD
               A4,1,1
      CAL
               MASK
A21
      ARS
               **
      ANA
               ** , 2
      LGR
               **
      RQL
               1
      LGL
               2
      CAS
               THREE
                                  IS THIS ELEM BLACK
      TRA
               Α3
                                    =WHITE ELEM.
      NOP
      TRA
               A6
                                    =BLACK ELEM.
A3
      CLA
               A21
      ADD
               SIX
      STO
               A21
      CLA
               MASK1
      ANA
               A21+2
      SUB
               SIX
      STA
               A21+2
      CLA
               RTS
      ADD
               ONE
      STO
               RTS
                                  NEXT INST FOR NEW WORD
      TIX
               A21-1,1,1
A4
               A21,0
      SXA
      CLA
               TTHREE
      STA
               A21+2
      AXT
               6,1
      TIX
               A21-1,2,1
A 5
      CLA
               RTS
      LGR
               12
      CLA
               LFS
      LGL
               12
      STO
               CRI,4
                                    LAST INTERVAL IN ROW TO CRI
A501
                             13 THIS THE FIRST ROW
      ZET
               LINES
      TXI
               B1,4,-1
                                    NOT FIRST ROW
```

```
AXT
                0.2
                               ASSESS. REG. NOS. TO ALL FRE
       TXI
                * + 1 9 4 4 - 5
       SXD
                A52+294
      PXA
                ڪءُ پ
      PAC
                ç 4
      SXA
                LENG,4
A51
      CLA
                REGNS
      ADD
                ONE
       SIC
                REGNS
                24
      ORA
                CRI,2
                                REG. NO. TO CRI
      SLW
                                     CRI TO PRI
                PRI:2
      TSX
                XYCOOR : 1
      C & 5
                CON
      ADD
                REGNS
                                     =EFFECTIVE ADDRESS FOR REG SIZE
       574
                A52
      CAL
                MASK2
                DRI.2
      ANA
      ARS
                12
      SLW
                TEMP
      CLA
                MASKI
      ANA
                PR1 , 2
      SUB
                TEMP
       ADD
                ONE
A52
      STO
                黄黄
                                     SIZE OF CRI TO TABLE DEGCT
      TXI
                1-0501+*
       TXH
                A51 52 0 **
                ONE
       CLA
       510
                LINES
       STO
                LF'S
      STZ
                PRI,2
                                     END OF TABLE PRI
      TRA
                ΧO
A5A
      CLA
                CONS
                                     THIS INST. WHEN ROW IS ALL BOL
      STO
                D2
       TRA
                Di
                CONZ
      CLA
       STO
                DZ
      STZ
                LENG
      STZ
                PRI
      STZ
                PRI+1
      CLA
                TTHREE
      STA
                A1+2
      SXA
                A1,0
      TRA
                D2+9
A.6
      CLA
                RTS
      LGR
                12
      CLA
                LFS
      LGL
                12
       510
                CRI94
                                    LESOPIS TO CRI
      CLA
                RIS
      ADD
                TWO
      STO
                LES
      CLA
                A21
                                                   Figure 6 - Sheet 3
```

```
SIX
      ADD
      STA
               A1
      CLA
               MASKI
      ANA
               A21+2
      SUB
               SIX
      STA
               A1+2
      CLA
               CON3
      STA
               A2 - 1
                                    GO TO FIND BEGINNING OF NEXT INTERVAL
      TXI
               A11,4,-1
A7
      CLA
               CON4
      STA
               A2-1
                                    GO TO END OF ROW ROUTINE
      TXI
               A501,4,1
B1
      AXT
               0,1
      AXT
               0,2
               PRI,1
      CAL
      TZE
               C2
                                    1. IF C GRTR THAN B+1 GET NEXT PRI
      CAL
               MASK1
                                    2. IF D LESS THAN A-1 GET NEXT CRI
      ANA
               PRI 1
                                    3. IF NEITHER 1 NOR 2 THEN CRI AND
      ADD
               ONE
      LGR
               36
                                        PRI OVERLAP
                                        (A,B DESIGNATE INTERVAL FOR PRI AND
      CAL
               MASK2
                                        C.D FOR CRI)
      ANA
               CRI,2
      ARS
               12
                                    TRA IF C GRTR THAN B+1
      TLQ
               C1
      CLA
               MASK1
      ANA
               CRI,2
      LGR
               36
               MASK2
      CAL
      ANA
               PRI .1
      ARS
               12
               ONE
      SUB
                                    TRA IF D LESS THAN A-1
      TLQ
               C2
               MASK3
                                    CRI AND PRI OVERLAP
      CAL
       ANA
               CRI 2
      TNZ
               B3
                               TRA IF CRI HAS A REG. NO.
      CAL
               MASK3
               PRI,1
       ANA
                                    REG = OF PRI TO CRI
      ORS
               CRI,2
               24
       ARS
       ADD
               CON
               B2
       STA
       STA
               B2+1
       CAL
               MASK2
       ANA
               CRI,2
       ARS
                12
       STO
               TEMP
       CLA
               MASK1
               CRI,2
       ANA
       SUB
                TEMP
               ONE
       ADD
                                     SIZE OF CRI + ACCUMULATED SIZE OF
B2
       ADD
                **
                **
                               REG. OF PRI TO (REGCT+REG.NO. OF CRI)
       STO
       TRA
                B5
```

Figure 6 - Sheet 4

```
B? THRU BE-1 ELIMINATES REDUNDANT REG NO.
B3
      SLW
                TEMP
                                                                            1
       CAL
               MASKE
                                                                            2
                PRI.1
                                                                            3
       ANA
                CMPT
                                                                            4
       LAS
                £+2
       TRA
               B5
                           DO NOT ELIMINATE IF REG NOS. ARE EQUAL
                                                                            Ć
       TRA
               MASK3
       CAL
               PRI .1
       ANA
       SLW
                TEMP
                24
       ARS
       ADD
               CON
       STA
               B31+1
       CAL
               MASK3
       ANA
                CRI .2
       ARS
                24
       ADD
               CON
       STA
               B31
       STA
               B31+2
B31
                                     REG SIZE OF REG OF PRI + REG
      CLA
                * *
       ADD
                **
                                     SIZE OF REG OF CRI TO REG SIZE
       STO
                                     OF CRI
                ××
       SXA
                STOR,1
       AXT
                0,1
B32
       CAL
               MASK3
       ANA
                PRI 1
       TZE
                                     ZEROES INDICATE END OF TABLE PRI
                B33
       LAS
                TEMP
                               NOT EQUAL TO REG. NO. OF REDUNDANT REG.
       TXI
                B32,1,-1
       TRA
                *+2
                               =REG. NO. OF REDUNDANT REG.
       TXI
                B32,1,-1
                                     NOT EQUAL
       CAL
                MASK1
       ADD
                MASK2
       ANS
                PRI 1
       CAL
                MASK3
       ANA
                CRI,2
       ORS
                PRI,1
                               REG. NO. OF CRI TO PRI
       TXI
                B32,1,-1
B33
       PXA
                                                                             1
                , 2
       TZE
                                                                             2
                B34+1
       SXD
                                                                             3
                B34,2
       AXT
                0,1
       CAL
                MASK3
       ANA
                CRI 1
       LAS
                TEMP
       TXI
                B34,1,-1
                *+2
                               = REG. NO. OF REDUNDANT REG.
       TRA
       TXI
                B34,1,-1
       CAL
                MASK1
       ADD
                MASK2
       ANS
                CRI 1
       CAL
                MASK3
       ANA
                CRI,2
                               REPLACE REDUNDANT REG. NO.
       ORS
                CRI,1
```

Figure 6 - Sheet 5

	TXI	*+1,1,-1	
B34	TXH	833+4.1.	
	LXA	STOR,1	
	CLA	TEMP	
	ARS	24	
	ADD	CON	
	STA	*+1	
	STZ	**	CLEAR REG SIZE OF REDUNDANT REG
	CLA	DUPS	CELAR REG SIZE OF REDUNDANT REG
	ADD		
		ONE	
	STO	DUPS	
	ADD	CON6	
	STA	*+5	
	CLA	MASK3	
	ANA	CRI,2	
	ARS	24	
	ADD	TEMP	
	510	* *	
B5	CAL	MASK1	
	ANA	PRI,1	
	STO	TEMP	
	CAL	MASK1	
	ANA	CRI,2	
	CAS	TEMP	
	TRA	C1	AC GRIR THAN TEMP, GET NEXT PRI
	TXI	*+5,1,-1	AC=TEMP, GET NEXT PRI AND CRI
	TXI	*+1,2,-1	AC LESS THAN TEMP, GET NEXT CRI
	SXD	*+1,4	
	TXL	D1,2,**	TRA IF NO MORE CRI
	TRA	B1+2	
	CAL	PRI,1	
	TNZ	*-5	TRA IF MORE PRI
	TXI	*-6,1,1	- · · · · · · · · · · · · · · · · · · ·
C 1	TXI	*+1,1,-1	
	CAL	PRI,1	
	TNZ	B1+2	TRA IF MORE PRI
	TXI	*+1,1,1	THE THE PART OF TH
C 2	CAL	MASK3	
	ANA	CRI,2	
	TNZ	C3	TRA IF CRI HAS A REG. NO.
	CLA	REGNS	THE TECHT HAS A REG NO.
	ADD	ONE,	
	STÖ	REGNS	
	ALS	24	
	ORS	CRI•2	REG. NO. TO CRI
	ARS		REG. NO. TO CRI
		24	
	ADD	CON	
	STA	C21	
	SXA	TEMP,1	
	TSX	XYCOOR,1	
	LXA	TEMP , 1	
	CAL	MASK2	
	ANA	CRI , 2	Figure 6 - Sheet 6
			1 + gare 0 - blieer 0

```
ARS
                12
                TEMP
       STO
       CLA
                MASK1
       ANA
                CRI,2
                TEMP
       SUB
       ADD
                ONE
C21
                **
       STO
                                SIZE OF CRI TO (REGCT+REG.NO. OF CRI)
C3
       IXT
                *+1,2,-1
       SXD
                *+194
       TXL
                D1,2,**
                                      TRA IF NO MOPE CRI
       TRA
                B1+2
D1
       CAL
                =2B17
       CALL
                (STB)
                                      INTERVALS TO TAPE
       SXA
                TEMP,2
       AXT
                0.2
       LDQ
                LENG
                                      VECTOR LENGTH
       STR
BCK
       LDQ
                PRI,2
       STR
       TXI
                *+1,2,-1
       CLA
                PRI,2
       TNZ
                BCK
       CALL
                (WLR)
       LXA
                TEMP, 2
       STZ
                PRI,2
D2
       NOP
       PXA
                , 2
       PAC
                ,2
       SXA
                LENG.2
       PAX
                ,2
       TXI
                *+1,2,1
       CLA
                CRI,2
       STO
                PRI,2
       TXH
                *-3,2,0
       CLA
                LINES
       ADD
                ONE
       STO
                LINES
       LXA
                LINES,1
                D3 > 1 ... **
Office
       TXH
       CFA
                ∟FS
       510
       TRA
                XΟ
                                      GO TO READ IN NEXT ROW
D3
       CAL
                =6817
       CALL
                (STH)
       PZE
                FORM, 0,1
       AXT
                8,1
D4
       LDQ
                HEAD+8,1
       STR
                                      HEADING TO OP
       TIX
                D49191
       STZ
                TEMP
       AXT
                -1,1
D5
       CLA
                TEMP
       ADD
                ONE
```

Figure 6 - Sheet 7

```
STO
                 TEMP
        CLA
                 REGCT , I
        TZE
                 D6
       LDQ
                 TEMP
        STR
                                      REG NO. TO OP
        CLA
                 MASKI
        ANA
                 XYCRD .1
        XCA
        STR
                                      ROW NO. TO OP
        CLA
                 XYCRD + 1
        ARS
                 12
        X \subset A
        STR
                                      COL NO. TO OP
        LDQ
                 REGET 41
        STR
                                      REG SIZE TO OP
06
        CLA
                 REGNS
       645
                 TEMP
        TXI
                 05,1,-1
        NOP
                 (FIL)
        CALL
        CALL
                 REWIP
        PZE
                 27
        CALL
                 REWIR
        PZE
                 721
        TRA
                 P0-3
        PZE
221
                 8,0,0
 ZZ
        PZE
                 0.0.2
 THREE OCT
                 3
DUPS
        OCT
                 0
        BSS
                 100
CON6
        STO
                 DUPS
XYCOOR CLA
                 CON5
        ADD
                 REGNS
        STA
                 XYR
        STA
                 XYC
        CLA
                 LIMES
        ADD
                 ONE
 XYR
        510
                 许 黄
                                      ROWLY COORDINATES TO XYCRD
        CLA
                 MASKE
        ANA
                 CRI92
 XYC
        ORS
                 * *
                                      COLIX COORDINATE: TO XYCRD
        TRA
                 1,1
ONE
        OCT
                 1
 TWO
        OCT
                 2
 SIX
        OCT
                 6
TTHREE DEC
                 33
MASK
       OCT
                 130000000000
MASKI OCT
                 000000007777
MASK2 OCT
                 000077770000
MASK3 OCT
                 777700000000
 CON
        STO
                 REGCT
 CON2
        NOP
 CON3
        PZE
                 A7
```

```
CON4
LINES OCT
               0
REGNS OCT
               0
LFS
      OCT
               1
RTS
      BSS
               1
TEMP
      BSS
               1
      855
               1
STOR
                              TABLE OF PREVIOUS ROW INTERVALS
PRI
      855
               100
               100
                              TABLE OF CURRENT ROW INTERVALS
CRI
      BSS
GRID
      BSS
               288
REGCT BSS
                              TABLE OF ACCUMULATED REGION COUNTS
               500
      PZE
LENG
               0
CON5
      STO
               XYCRD
XYCRD BSS
               500
                              TABLE OF X-Y COORDINATES
FORM
      BCI
               5,(8A6//(1J12,1J12,1J4,1J16))
HEAD
      BCI
               5,1 REGION NUMBER
                                       ROW COL
                     REGION SIZE
      BCI
               3,
SEV
      OCT
               7
      AXT
               500,1
      STZ
               XYCRD+500.1 CLEAR TABLE XYCRD
      XIT
               *-1,1,1
PO
      AXT
               ** , 1
      CLA
               CON7
               GRID
      STO
      CAL
               =2817
      CALL
               (TSB)
      STR
      XCA
                     1ST WORD CONTAINS NO. OF WORDS IN RECORD
      STO
               LENG
      TZE
               010
                                                                            1
      PAX
               94
      PAX
               92
      ADD
               BCK
      STA
               Pl
                                    = 'PRI' + NO. OF WORDS IN RECORD
      STA
               Q6
      STA
               P4
               P6
      STA
      STA
               *+2
      STR
               ** 4
      STQ
      TIX
               *-2,4,1
      CALL
               (RLR)
P01
      LXA
               DUPS,4
      CLA
               CON6
      ADD
               DUPS
      ADD
               ONE
      STA
               P1+3
      CLA
               MASK3
P1
      ANA
               **,2
                                    EXTRACT REG. NO.
      STO
               TEMP
      CLA
               MASK3
      ANA
               **94
                            EXTRACT DUP
      CAS
               TEMP
                                                  Figure 6 - Sheet 9
```

PZE

A5A

	TRA	*+2	
	TRA	Q1	TRA IF REG. NO. IS A DUP
	TIX	P1+2,4,1	TRA IT REGO NOS IS A DOP
	CAL	TEMP	
	ARS	24	
	ADD	CON5	
	STA	P5	=EFFECTIVE ADDRESS OF SYMBOL ASSIGNED
	STA	P3	TO REG. NO.
	STA	*+1	
	CAL	**	
	TNZ	P4-1	TRA IF REG. HAS A SYMBOL
	CAL	MASK4	
P2	ARS	0	
	ANA	SYM	GET NEW SYMBOL FOR THIS REG.
	ALS	0	
P3	SLW	**	
	CLA	MASK1	
	ANA	P2	
	ADD	SIX	
	LDQ	TTHREE	
	TLQ	Q2	TRA IF NEW WORD OF SYM IS NEEDED
P31	STA	P2	
	STA	P3-1	
	CLA	COUNT	
	ADD	ONE	
	STO	COUNT	
	LDQ TLQ	FFIV Q9	TRA IF ALL SYMS. HAVE BEEN USED
	CLA	MASK2	TRA IT ALL STAS. HAVE BEEN USED
Р4	ANA	**,2	EXTRACT LES OF CURRENT INTERVAL
•	ARS	12	Control of Control of the Control of
	LDQ	ELEM	
	TLQ	Q4	TRA IF CURRENT COL IS LESS THAN LFS
	CAL	MASK4	
P41	ARS	0	
	COM		
	ANA	** , 1	
	SLW	**,1	
P5	CAL	**	
	ARS	O	
	ORS	**,1	SYMBOL TO GRID
	CLA	MASK1	
	ANA	P41	
	ADD	SIX	
	LDQ	TTHREE	TO A SE NEW HORD OF COID IS NEEDED
0.51	TLQ	Q3	TRA IF NEW WORD OF GRID IS NEEDED
P51	STA	P41 P5+1	
	STA	ELEM	
	CLA ADD	ONE	
	STO	ELEM	
	CLA	MASK1	
P6	ANA	**,2	EXTRACT RTS OF INTERVAL
. 0	, , , , ,	,	Figure 6 - Sheet 10

```
ELEM
      CAS
      MOP
                                    TRA IF END OF INTERVAL NOT YET REACHED
      TRA
               P41-1
               P01,2,1
      TIX
                                    ALL INTERVALS IN ROW THE PROCESSED
               Q7
      TRA
Q1
               MASK1
                                    REPLACE DUP REG. NO.
      CLA
                                    EXTRACT REPLACING REG. NO.
               P1+3
      ANA*
               P1
      LDQ*
      RQL
                12
                24
      LGL
               P1
      SLW*
               P01
      TRA
Q2
                                GET NEXT WORD OF SYMBOLS
      CLA
               MASK5
       ANA
               P2 + 1
       ADD
                ONE
                P2+1
       STA
      PXA
                • 0
       TRA
                P31
Q3
       TIX
                *+2,1,1
                Q5
                                    TRA IF ROW IS COMPLETED
       TRA
       CLA
                CON7
       STO
                **,1
       PXA
                •0
       TRA
                P51
Q4
       CLA
                ELEM
       ADD
                ONE
                ELEM
       STO
       CLA
                MASK1
       ANA
                P41
       ADD
                SIX
                TTHREE
       LDQ
                *+4
       TLQ
Q41
       STA
                P41
                P5+1
       STA
       TRA
                P4-1
                *+2,1,1
       XIT
       TRA
                Q5
       CLA
                CON7
                **,1
       STO
       PXA
                • 0
       TRA
                Q41
                                     ROW IS COMPLETED
Q5
       CAL
                =6B17
       CALL
                (STH)
                                                                            1
       PZE
                FRMT,0,1
                **,1
       AXT
                CON7
       LDQ
       STR
       LDQ
                **,1
                                     ROW J OF GRID TO TAPE
       STR
       TIX
                *-2,1,1
                (FIL)
       CALL
       CAL
                =3B17
       CALL
                (STB)
                                                    Figure 6 - Sheet 11
```

```
LENG
       LDQ
                                     ROW J OF INTERVALS TO TAPE
       STR
       E.XA
                LFNG.1
Q6
       LDQ
                # × 9 ]
       STR
                *-2,1,1
       TIX
       CALL
                (WLR)
                ROW
       CLA
                ONE
       ADD
       STO
                ROW
                ROW
       LDQ
       CLA
                ENDR
       TLQ
                Q8
       CALL
                REWTP
       PZE
                Z Z
       CALL
                RUNTP
                                     REWIND TAPE ON UNIT 3
       PZE
                ZZ2
       TRA
                011
272
       PZE
                0.0.3
Q7
       TIX
                *+2,1,1
                            REST OF THE ROW IS BOUNDARY
       TRA
                Q5
       CLA
                CON7
       STO
                **,1
       TRA
                Q7
Q8
       CLA
                ONE
       STO
                ELEM
       PXA
                • 0
       STA
                P41
                P5+1
       STA
       TRA
                PO
                                     RETURN FOR NEXT ROW
09
       CLA
                CONB
       STA
                P2+1
       STZ
                COUNT
       PXA
                • 0
       STA
                P2
                P3-1
       STA
       TRA
                P4-1
Q10
       CALL
                (RLR)
       TRA
                Q7
CON7
       BCI
                1,
CON8
       PZE
                SYM
CON9
       TRA
                A5A+3
MASK4 OCT
                770000000000
ELEM
       OCT
                1
FFIV
       DEC
                45
COUNT OCT
                0
ROW
       OCT
                0
SYM
       BCI
                8,ABCDEFGHIJKLMNOPQRSTUVWXYZ123456789+-/= 1.) 5*, (
FRMT
       BCI
                2,(1H9,20A6)
                000000077777
MASK5 OCT
Q11
       LXA
                CON10,1
       TXI
                *+1,1,-3
                CON10,1
       SXA
                                              Figure 6 - Sheet 12
```

1

2

3

```
CLA
               ENDR.1
                            TRA IF NO MORE PASSES REQUIRED
      TZE
               012
               ENDR
      STO
      CLA
               BEGW , 1
               BEGW
      STO
      CLA
               ENDW . 1
      510
               ENDW
      CLA
               ONE
      STO
               LFS
      STO
               ELEM
      STZ
               LINES
      STZ
               REGNS
      STZ
               COUNT
      STZ
               ROW
      CLA
               CON8
      STA
               P2+1
      STZ
               DUPS.
      PXA
               90
      STA
               P2
               P3-1
      STA
      STA
               P41
      STA
               P5+1
      TRA
               X 1
Q12
      CALL
               (SPH)
                            PRINT ON-LINE
      PZE
               FMT,0,1
      AXT
               5,1
               TAPE+5,1
      LDQ
      STR.
      TIX
               *=2,1,1
      HPR
      CALL
               EXIT
FMT
      BCI
               1,(5A6)
CON10 DEC
               5, END OF JOB - DISMOUNT TAPES
TAPE
      BCI
ENDR
      DEC
               289
                            ENDING ROW
BEGW
      DEC
                            BEGINNING WORD
               1
ENDW
      DEC
               19
                            ENDING WORD
               289
                            EACH SET OF 3 CARDS WIKL CAUSE THE
      DEC
                            PROGRAM TO MAKE ONE PASS ON A PICTURE.
      DEC
               62
                            THE LAST SET OF 3 CARDS MUST BE FOLLOWED
      DEC
               80
                            BY A WORD OF ZEROES.
      DEC
               0
      END
```

4

2.

6

3. REST: Region-Enclosed Square Tabulator

3.1 General description

The principal function of REST is to compile a frequency distribution of the squares of various sizes lying within each connected region (as defined for RAMP) on a set of pictures. The range of desired sizes, the picture size, and the number of pictures to be processed are specified by the user. These dimensions are all specified in terms of numbers of picture elements.

For each square size considered within a given region, the following information is computed in addition to the square frequency count:

- The frequency of exterior squares (with at least one element touching the boundary of the region)
- . The frequency of interior squares (with no element touching the boundary)
- . The percentage of squares which are exterior
- . The percentage of squares which are interior

Picture data are input to the program from magnetic tape, line by line. Regions are represented by the picture-element intervals which they occupy on each line; a number assigned to each interval indicates its region. The picture interval data are produced by RAMP from an elementby-element digital picture representation as described in Section 2. A sample picture consisting of ten regions, in the form produced as output by RAMP, is shown in Figure 7. A line drawing representation of this picture is shown in Figure 2, column 1, picture 6. The output of REST for this picture is shown in Figure 8.

3.2 Input

The number of records on the magnetic input tape is equal to the total number of lines in the set of pictures to be processed. Each record contains information about one line in the picture.

The first word of the record contains the number of intervals on the line. Each succeeding word, representing one interval, is divided into three parts of four octal digits each. The first part is the interval region number; the second, the interval left end element number; the third, interval right end element number.

Elements are numbered consecutively from 1 to P, where P is the picture width.

For example, the input record representing line 11 of the sample picture (Figure 7) is:

00000000005 014300010007 013300130050 013400540114 013501210130 013401330162

The region represented by M in the picture was assigned identifying number 143 (octal); by J, identifying number 133; etc.

3.3 Operating parameters

REST is coded in the FAP assembly language to run on an IBM 7090 computer. For input-output a University of Maryland modified FORTRAN Input-Output-Hollerith program was used.




FIGURE 7
TYPICAL INPUT TO REST

	Square	Square Frequencies			Square Percentages	
Region	Width	Total	Exterior	Interior	Exterior	Interior
L	2	190	111	79	58	42
	3	131	89	42	68	32
	4	79	56	23	71	29
	5	42	32	10	76	24
	6	23	21	2	91	9
	7	10	10	0	100	0
	8	2	2	0	100	0
	9	0	0	0	0	0
J	2	1022	208	814	20	80
	3	913	187	726	20	80
	4	814	172	642	21	79
	5	726	164	562	23	77
	6	642	156	486	24	76
	7	562	148	414	26	74
	8	486	139	347	29	71
	9	414	131	283	32	68
	10	347	123	224	35	65
	11	283	113	170	40	60
	12	224	103	121	46	54
	13	170	96	74	56	44
	14	121	78	43	64	36
	15	74	56	18	76	24
	16	43	40	3	93	7
	17	18	18	0	100	0
	18	3	3	0	100	0
	19	0	0	0	0	0

Figure 8
Output of REST for the Input of Figure 7

Region	Square Width	<u>Total</u>	Square Frequencie Exterior	S Interior	Square Per	rcentages Interior
					<u> </u>	111001101
ĸ	2	3072	402	2670	13	87
	3	2869	395	2474	14	86
	4	267 0	388	2282	15	85
	5 6	2474	380	2094	15	85
	6	2282	37 0	1912	16	84
	7	2094	360	1734	17	83
	8	1912	352	1560	18	82
	9	1734	343	1391	20	80
	10	1560	335	1225	21	79
	11	1391	326	1065	23	77
	12	1225	317	908	26	74
	13	1065	310	755	29	71
•	14	908	284	624	31	69
	15	755	250	505	33	67
	16	624	228	396	37	63
	17	505	196	309	39	61
	18	396	143	253	36	64
	19	309	103	206	33	67
	20	253	89	164	35	65
	21	206	80	126	39	61
	22	164	72	92	44	56
	23	126	64	62	51	49
	24	92	56	36	61	39
	25	62	46	16	74	26
	26	36	33	3	92	8
	27	16	16	0	100	0
	28	3	3	0	100	0
	29	0	0	0	0	0
0	2	413	112	301	27	7 3
	3	355	100	255	28	72
	3 4	301	88	213	29	71
	5	255	79	176	31	69
	6	213	71	142	33	67
	7	176	65	111	37	63
	8	142	59	83	42	58
	9	111	53	58	48	52
	10	83	46	37	55	45
	11	58	39	19	67	33
	12	37	32	5	86	14
	13	19	19	Ö	100	0
	14	5	5	Õ	100	Õ
	15	Õ	Ō	Ö	0	Ö
P	2	144	67	47	59	41
	3	76	48	28	63	37
	4	47	34	13	72	28
	5	28	25	3	89	11
	6	13	13	0	100	0
	2 3 4 5 6 7	3	3	Ō	100	0
	8	13 3 0	13 3 0	0	0	Ō

	Square	square Frequencies			Square Pe	ercentages
Region	Width	Total	Exterior	Interior	Exterior	Interior
N	2	1531	237	1294	15	85
14	3	1410	228	1182	16	84
	4	1294	220	1074	17	83
	5	1182	211	971	18	82
	6	1074	200	874	19	81
	7	971	188	783	19	81
	8	874	176	698	20	80
	9	783	164	619	21	79
	10	698	154	544	22	78
	11	619	146	473	24	76
	12	544	138	406	25	75
	13	473	130	343	27	73
	14	406	122	284	30	70
	15	343	115	228	34	66
	16	284	107	177	38	62
	17	228	100	128	44	56
	18	177	9 4	83	53	47
	19	128	85	43	66	34
	20	83	69	14	83	17
	21	43	40	3	93	7
	22	14	14	0	100	0
	23	3	3	0	100	0
	24	0	0	0	0	0
Q	2	85	76	9	89	11
	3	40	40	0	100	0
	4	9	9	0	100	0
	5	0	0	0	0	0

	Square	Square Frequencies		Square Percentages		
Region	Width	Total	Exterior	Interior	Exterior	Interior
_	-	1200	100			- •
R	2	1388	199	1189	14	86
	3 ,	1286	189	1097	15	85
	4	1189	179	1010	15	85
	5	1097	171	926	16	84
	6	1010	164	846	16	84
	7	926	156	770	17	83
	8	846	149	697	18	82
	9	770	143	627	19	81
	10	697	137	560	20	80
	11	627	129	498	21	79
	12	560	120	440	21	79
	13	498	113	385	23	77
	14	440	106	334	24	76
	15	385	100	285	26	74
	16	334	94	240	28	72
	17	285	88	197	31	69
	18	240	83	157	35	65
	19	197	76	121	39	61
	20	157	69	88	44	56
	21	121	64	57	53	47
	22	88	59	29	67	33
	23	57	51	6	89	11
	24	29	29	0	.100	0
	25	6	6	0	100	0
	26	0	0	0	0	0

Region	Square <u>Width</u>	Total Sc	uare Frequencie Exterior	Interior	Square Per Exterior	rcentages Interior
S	2 3 4	14 4 0	14 4 0	0 0 0	100 100 0	0 0 0
M	2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29	5343 4928 4541 4178 3830 3493 3193 2910 2644 2392 2164 1947 1737 1535 1341 1158 982 813 658 517 402 302 214 142 90 54 30	802 750 711 685 637 583 549 518 480 445 427 412 396 377 359 345 324 296 215 188 160 124 88 60 43 29 11	4541 4178 3830 3493 3193 2910 2644 2392 2164 1947 1737 1535 1341 1158 982 813 658 517 402 302 214 142 90 54 30 11	15 15 16 16 17 17 17 18 18 19 20 21 23 25 27 30 33 36 39 42 47 53 58 62 67 80 97 100	85 84 84 83 83 83 82 82 81 80 79 77 75 73 70 64 61 58 53 47 42 38 33 20 30
	30 31	0	1 0	0 0	100 0	0 0

Figure 8 Sheet 5

The following parameter cards must be supplied for each program run:

Symbolic Location and Contents			Card Number*	Parameter Definition	Parameter Limits
WMIN	DEC	W_{\min}	3790	Minimum square width to be considered	l to W _{max}
WMAX	DEC	W _{max}	3800	Maximum square width to be considered	l to P _{wd}
PLC	DEC	P_{lc}	3792	Picture length (number of lines per picture)	l to magnetic tape storage limit
WP	DEC	w_p	3834	Number of pictures	l to magnetic tape storage limit
PICWID	DEC	P_{wd}	3819	Picture width (number of picture elements per line)	l to 1000 (providing number of different regions per line does not exceed 60)

3.4 Logical description

One line of picture elements is read in from magnetic tape at a time. The program assigns a column height to each element of the line as follows. The column heights of elements within an interval are incremented by 1; the column heights of elements not in an interval are reset to zero. Initially all column heights are set to zero.

Each interval is processed as follows: The region number of each interval (a, b) is examined to see whether it is in a previously processed region. If not, the region number, row number, and column *As shown on the assembly listing of the program (Figure 10)

number are placed in an empty line of the Region Table. A flag, called the usage indicator, which is explained later on, is set for this region.

Each element within the current interval is examined to see whether it will complete a square of the width being considered (the current width). A square width counter is reset to zero at the beginning of the interval. For each element of the interval, processing proceeds as follows: If the column height is found equal to or greater than the current width, the current square is "high" enough, and therefore the square width counter is incremented by 1. If now, the square width counter itself equals or exceeds the current width, the current square is also "wide" enough, and therefore the frequency of squares of the width being examined for the region in process is incremented by 1.

If the column height is too small, the square width counter is reset to zero. (The square width counter thus represents the number of consecutive columns which are "high" enough.) This is done for all square widths from WMIN to WMAX by setting the current width first to WMIN and incrementing it by 1 up to and including WMAX. However, if the frequency of the squares of some width W less than WMAX is found to be zero, the square sizes W + 1,..., WMAX are not considered. Succeeding intervals are processed in the same fashion.

Important to the program are the <u>usage indicators</u> referred to above. There is one usage indicator for each line of the Region Table, which

holds information about regions currently in process. Initially all the usage indicators are set to zero. If the region number for an interval matches none in the Region Table, this indicates a new region to be processed. A new entry is made for this region into the first empty line of the table, i.e., the first line whose usage indicator is zero. This usage indicator is then reset to 1, indicating that this region is now in process. If a region of the interval has been processed in the preceding line (i.e., if the region number matches one already in the table), the usage indicator for that region in the Region Table is reset to 1, indicating that this region is still in process.

When all the intervals of a line have been processed, each usage indicator is examined. If a usage indicator is 1, that line of the Region Table was in process in the present cycle (one picture line is processed each cycle); that usage indicator is reset to minus 1. If the usage indicator is initially minus 1, that line of the region was in process in the previous cycle but not in the present cycle. Therefore, this region is "closed out," and its data are ready for output. This usage indicator is reset to zero (indicating that its line in the Region Table can be reused subsequently), and data for that region are then output.

When outputting a line of the Region Table, the frequency of exterior and interior squares and the percentage of exterior and interior squares are obtained using the fact that the frequency of interior squares of width t is equal to the frequency of all squares of width (t + 2). The

frequency of exterior squares of width t is then equal to the frequency of total squares of width t minus the frequency of the interior squares of width t.

A flow chart and symbolic program listing for REST are shown as Figures 9 and 10.

Figure 9

REST Flow Chart




Figure 9 - Sheet 1





Figure 9 - Sheet 2



Store Line Number of Region Table being processed

Set Usage Indicator of ith line of Region Table = 1

(SIZE) = Number of elements in interval being processed

(WMAXP) = Maximum Square Size to be considered plus 2

Set Frequency Table for line number of Region Table being processed

Increment Column Heights in interval being processed by 1

Set Minimum Square Size (WMIN) to Current Square Size (WCUR)

Set Switch (which determines whether a square has been counted) = 0

Set Square Width Counter (J) = 0

Set Column Counter for Interval (K) = 0

Figure 9 - Sheet 3




Figure 9 - Sheet 4






Figure 9 - Sheet 5




Increase Current Square Size by 1

Is right endpoint of last interval in last column of line? (PICWID) = width of picture Set all column heights to right of last interval = 0

Figure 9 - Sheet 6








Figure 9 - Sheet 9





Figure 9 - Sheet 10



Set all column heights equal to zero

Figure 9 - Sheet 11

Figure 10

REST Symbolic Program Listing

```
REST
                        REGION ENCLOSED SQUARE TABULATOR
NEWPCT LXA
                REGNS . 1
       LXA
                REGNS, 2
       TXI
                *+1,2,USAGE
       SXA
                SC3BBB,2
       SXA
                SCANN, 2
       SXA
                USE 2
       SXA
                SC10A-2,2
       SXA
                SC10+1,2
       SXA
                SC10A-5,2
       SXA
                SC10A+1,2
USE
                             SET USAGE INDICATOR FOR EACH LINE OF TABLE=0
       STZ
                **,1
       TIX
                USE,1,1
                             NUMBER OF REGIONS PLUS ONE INTO 1R4
       LXA
                REGNS 4
       LXA
                REGNS . 1
                             NUMBER OF REGIONS PLUS ONE INTO IR1
       TXI
                *+1,1,REGTB
       SXA
                SC10+3,1
                             SET UP ADDRESS FOR OUTPUTTED REGION NUMBER
       SXA
                SCAN+191
       SXA
                BACK 1
BACK
       STZ
                **•4
                             SET ALL REGION NUMBERS IN TABLE EQUAL TO ZERO
                BACK,4,1
       TIX
       AXT
                7200,2
                7200,4
       AXT
       TXI
                *+1,4,FRECT
                FRETA,4
       SXA
FRETA
       STZ
                ** 2
                             CLEAR ALL FREQUENCIES
       TIX
                FRETA, 2, 1
       LXA
                PICWID,4
                             PICTURE WIDTH INTO IR4
       LXA
                PICWID,1
                             PICTURE WIDTH INTO IR1
       TXI
                *+1,1,COLM
       5XA
                LAST+2,1
       SXA
                COLUMN,1
COLUMN STZ
                             SET ALL COLUMN HEIGHTS EQUAL TO ZERO
                **,4
       TIX
                COLUMN, 4,1
SCO
       CAL
                =6B17
       CALL
                (STH)
                                     HEADINGS
       PZE
                FORM, 0,1
       AXT
                20,1
D4
       LDQ
                FHEAD+20,1
       STR
       TIX
                D4,1,1
       AXT
                20.1
D5
       LDQ
                HEAD+20,1
       STR
       TIX
                D5,1,1
       CALL
                (FIL)
       CLA
                XAMW
                             MAXIMUM SQUARE SIZE TO BE CONSIDERED
                             MINIMUM SQUARE SIZE TO BE CONSIDERED
       SUB
                WMIN
       ADD
                ONE
       STO
                RANGE
                             NUMBER OF SQUARE SIZES
SC1
                PLV
                             INITIALIZE PICTURE LINE COUNTER
        STZ
SC1A
                             ANY MORE LINES OF
       CLA
                PLC
                                     PICTURE TO PROCESS.
        SUB
                PLV
```

Figure 10 - Sheet 1

```
VARING TZE
                VC
       CLA
                PLV
                                    OBTAIN NEXT LINE
       ADD
                                    PLV EQUALS PLV PLUS
                ONE
       STO
                PLV
                                    ONE
       CAL
                =9817
                                    READ IN NEXT LINE
                (TSB)
                                   OF PICTURE
       CALL
       STR
       STQ
                NUOIN
       CLA
                NUOIN
                             NUMBER OF INTERVALS
       TZE
                SC1E
       LXA
                NUOIN , 2
                             NUMBER OF INTERVALS INTO IR2
       LXA
                NUOIN 94
                             NUMBER OF INTERVALS INTO IR4
       TXI
                *+1,4,INTER
       SXA
                SC1C94
SC1B
                SC1D,2
       SXA
       STR
       STQ
                INTREV
                INTREV
       CLA
SC1C
       STO
                **<sub>2</sub>
SC1D
       AXT
                ** , 2
       TIX
                SC1B,2,1
SC1E
       CALL
                (RLR)
                             READ IN PRESENT LINE
       CLA
                NUOIN
                             NUMBER OF INTERVALS
       TZE
                LAST
                             NUMBER OF INTERVALS INTO IR2
       LXA
                NUOIN,2
SC2A
       LXA
                NUOIN 4
                             NUMBER OF INTERVALS INTO IR4
       TXI
                *+1,4,INTER
       SXA
                SC2D,4
       SXA
                SC3AA94
       SXA
                SC2BB,4
       SXA
                SC2BBB,4
       SXA
                SC3 , 4
       SXA
                SC3AAA,4
       SXA
                INTEG 4
                             INITIALIZE RIGHT SIDE OF PREVIOUS INTERVAL
       STZ
                PRERIN
SC2B
       CAL
                MASK3
INTEG
       ANA
                ×ו2
                                    OBTAIN RIGHT MEMBER OF INTERVAL
       STO
                RIN
SC2B6
       CAL
                **,2
       ARS
                12
SC2BBB STO
                **,2
                MASK3
       CAL
SC2D
       ANA
                **,2
                             LEFT SIDE OF INTERVAL
       STO
                LIN
       CLA
                             LEFT SIDE OF INTERVAL
                LIN
                             RIGHT SIDE OF PREVIOUS INTERVAL
       SUB
                PRERIN
       SUB
                ONE
       STO
                PRERIN
                             GAP BETWEEN INTERVALS
                PRERIN,4
                             INTO IR4
       LXA
                             LEFT SIDE OF INTERVAL INTO IRI
       LXA
                LIN,1
                *+1,1,COLM
       TXI
       TXI
                *+1,1,-1
       SXA
                ZEROOS,1
```

Figure 10 - Sheet 2

```
SC3C,1
       SXD
       SXA
                SC7,1
                SC8C,1
       SXA
                             LEFT SIDE OF INTERVAL
       CLA
                LIN
       SUB
                ONE
                SC3
       TZE
ZEROOS STZ
                             SET ALL COLUMN HEIGHTS BETWEEN LAST
                **,4
                ZEROOS,4,1
                            INTERVAL AND PRESENT INTERVAL EQUAL TO ZERO
       TIX
SC3
       CAL
                **,2
       ARS
                12
SC3AAA STO
                **,2
       CAL
                MASK3
SC3AA
       ANA
                **,2
       STO
                REGIO
                             REGION NUMBER OF INTERVAL
       LXA
                REGNS, 1
       TXI
                *+1,1,REGTB
       SXA
                ADDRE,1
       LXA
                REGNS,4
SCAN
       CLA
                REGIO
                             IS CURRENT INTERVAL IN
                **•4
                             A PREVIOUSLY PROCESSED REGION
       SUB
       TZE
                SC3B
       TIX
                SCAN, 4,1
       LXA
                REGNS,4
SCANN
                             SEARCH FOR FIRST EMPTY LINE OF REGION TABLE
       CLA
                **,4
       TZE
                0K
       TIX
                SCANN,4,1
       PXA
                ,4
OK
       STO
                LINE
       CLA
                REGIO
                             PLACE REGION NUMBER OF
ADDRE
       STO
                **,4
                             CURRENT INTERVAL IN REGION TABLE
                             NUMBER OF REGIONS INTO IR1
       LXA
                REGNS,1
       TXI
                *+1,1,ROW
                             SET UP ADDRESS FOR OUTPUTTED COLUMN NUMBER
                SC11A,1
       SXA
       SXA
                ADDRF,1
       CLA
                PLV
                             ROW NUMBER OF CURRENT LINE
ADDRF
       STO
                ** 4
                             NUMBER OF REGIONS INTO IR1
       LXA
                REGNS,1
       TXI
                *+1,1,COL
                             SET UP ADDRESS FOR OUTPUTTED COLUMN NUMBER
       SXA
                SC11B-2,1
       SXA
                ADDRG.1
                             LEFT SIDE OF INTERVAL
       CLA
                LIN
ADDRG
       STO
                **,4
SC3B
       PXA
                ,4
       STO
                LINE
       CLA
                SIXTY1
       SUB
                LINE
       STO
                LINE
       CLA
                ONE
SC3BBB STO
                **,4
       CLA
                RIN
                             RIGHT SIDE OF INTERVAL
                             LEFT SIDE OF INTERVAL
       SUB
                LIN
```

ADD

ONE

Figure 10 - Sheet 3

	STO	SIZE	SIZE OF INTERVAL PLUS ONE
	LXA	SIZEyI	
SC30	TXI	# + 1 + 1 + + +	UPDATE COLUMN COUNTER
	SXA	517 EY a:	COUNTER
	SXA	SIZEY+2,1	
	CLA	WMAX	MAXIMUM SQUARE SIZE BEING CONSIDERED
	ADD	TWO	THINKING TO SHOULD STEE BEING CONSIDERED
	STO	WMAXP	
	LDQ	LINE	
	MPY	WMAXP	
	XCA		
	STO	ADDER	
	LXA	ADDER • 1	
	TXI	*+1,1,FRECT	
	SXA	NEXT,1	
	SXA	NEXT+2,1	
	LXA	SIZE,4	
SIZEY	CLA	** 9 4	ADD ONE TO COLUMN
0 2 2 2 1	ADD	ONÉ	HEIGHTS IN THIS INTERVAL
	STO	**,4	HEIGHTS IN 11/12 INTERVAL
6.6.5	TIX	SIZEY,4,1	CET CURRENT OF THE TO
SC5	CLA	WMIN	SET CURRENT WIDTH TO
	STO	WCUR	MINIMUM COUNT WIDTH
	CLA	WMAX	MAXIMUM SQUARE SIZE TO BE CONSIDERED
	SUB	WMIN	MINIMUM SQUARE SIZE TO BE CONSIDERED
	ADD	= 3	
	STO	MRANGE	
	LXA	MRANGE \$4	
SC6	STZ	SWCH	SET SWCH EQUAL TO ZERO
	STZ	J	SET SQUARE WIDTH COUNTER EQUAL TO ZERO
	STZ	K	SET COLUMN COUNTER FOR THIS INTERVAL =0
SC7	CLA	**	IS SQUARE HEIGHT
00,	SUB	WCUR	LARGE ENOUGH.
	TMI	SC7A	LANGE ENGOGINE
	CLA	J	
		=	
	ADD	ONE	TO COLLAGE VIDEN
	STO	J	IS SQUARE WIDTH
	SUB	WCUR	LARGE ENOUGH.
<u>-</u>	TMI	SC7B	
NEXT	CLA	**94	ADD 1 TO FREQUENCY COUNT
	ADD	ONE	OF SQUARE OF SIZE WCUR,
	STO	**,4	REGION R.
	CLA	ONE	AT LEAST ONE SQUARE
	STO	SWCH	COUNTED THIS CYCLE.
	TRA	SC7B	
SC7A	CLA	ZERO	
	STO	J	
SC7B	CLA	K	COLUMN COUNTER FOR INTERVAL BEING PROCESSED
3610	ADD	ONE	COLONIA COOMPEN ON THIENAME DETMO PROCESSED
			COLUMN COUNTER FOR INTERVAL BEING PROCESSED
cco	STO	K	
SC8	CLA	K	IS IT END OF
	SUB	SIZE	CURRENT INTERVAL.

Figure 10 - Sheet 4

```
TZE
               SC8A
                SC? 91
                           GO TO NEXT
       LXA
                           COLUMN FOR
       TXI
                ** 1 9 1 9 1
               51731
                           COUNTING
       5 Y 4
       TRA
               SCT
SC8A
       CLA
               SWCH
                                   AT LEAST ONE SQUARE
                                   COUNTED THIS CYCLE.
       SUB
               ONE
       TNZ
               *+2
       TIX
               SC85,4,1
                                   LARGEST SQUARE SIZE
       CLA
               RIN
                            RIGHT SIDE OF INTERVAL
                            RIGHT SIDE OF PREVIOUS INTERVAL
       STO
               PRERIN
       TIX
               SC2B,2,1
                            ANY MORE INTERVALS THIS LINE
       TRA
               SC9
SC8B
       CLA
               WCUR
       ADD
               ONE
       STO
               WCUR
SC8C
       AXT
               **;]
       SXA
               SC7.1
       TRA
               SC6
SC9
       CLA
               RIN
                            RIGHT SIDE OF INTERVAL
       ADD
               ONE
               PICWID
       SUB
                            WIDTH OF PICTURE
       TPL
               SC9B
       CLA
               PICWID
       SUB
                            RIGHT SIDE OF INTERVAL
               RIN
                            LENGTH OF LAST GAP IN INTERVAL
       STO
               ENDING
                            LENGTH OF LAST GAP IN INTERVAL INTO IR4
       LXA
               ENDING,4
       LXA
                PICWID:1
                            PICTURE WIDTH INTO IRI
       TXI
               *+1,1,COLM
       SXA
                ZEROO,1
ZEROO
       STZ
               ** 94
                            SET ALL COLUMN HEIGHTS TO RIGHT OFINTERVAL=0
       TIX
                ZER00,4,1
                                   EQUAL TO ZERO
SC9B
       LXA
                REGNS 1
SC10
       CLA
                                   IS THIS LINE OF
               ZERO
       SUB
                                   REGION TABLE EMPTY.
                **,1
       TZE
                SC11
       CLA
                ** , ]
       STO
                                   REGION BEING CONSIDERED
               REGNC
                                   WAS THERE AN INTERVAL IN
       CLA
                ONE
                                   REGION R THIS CYCLE.
       SUB
                ** . ]
       TZE
                SC10A
       SXA
                SAVE 1
                            SET USAGE INDICATOR EQUAL TO ZERO
       STZ
                **.1
       TRA
                SC11A
SC10A
       CLS
                ONE
                                    SET USAGE INDICATOR EQUAL
                                    TO MINUS ONE
       STO
                **,1
SC11
       TIX
                SC10,1,1
       TRA
                SC1A
SC11A
                **,1
                           ROW NUMBER OF REGION BEING OUTPUTTED
       CLA
       STO
                ROWC
       CLA
                ** . 1
                COLC
       STO
```

Figure 10 - Sheet 5

```
, 1
SC11B
       PXA
        510
                LINE
       \subseteq [A
                SIXTYI
       SUB
                LINE
       STO
                LINE
       LDQ
                LINE
       MPY
                WMAXP
       XCA
       STO
                ADDER
       LXA
                ADDER . 4
       TXI
                *+1,4,FRECT
       SXA
                BEGIN.4
       TXI
                *+1,4,-2
       SXA
                SC21,4
       SXA
                URIGIN,4
       SXA
                DIVIDE, 4
       SXA
                BEGIN+2,4
       LXA
                              NUMBER OF SQUARE SIZES INTO IR2
                RANGE 32
BEGIN
       CLA
                ** ,2
       STO
                INT,2
                              FREQUENCY OF INTERIOR SQUARES
       CLA
                **,2
                                     UF INTERIOR SQUARES OF SIZE
       SUB
                              FREQUENCY OF INTERIOR SQUARES
                INT,2
       STO
                EXT,2
                              FREQUENCY OF EXTERIOR SQUARES
        TIX
                BEGIN, 2,1
       LXA
                RANGE , 2
                              NUMBER OF SQUARE SIZES INTO 1R2
ORIGIN CLA
                ** .2
                                     IS FREQUENCY OF SQUARES
        TZE
                ZEROIN
                                     EQUAL TO ZERO.
       CLA
                INT,2
                           FREQUENCY OF INTERIOR SQUARES
       TZE
                SC17
       XCA
       CLA
                ZERO
       MPY
                TWOHUN
DIVIDE DVP
                **,2
       XCA
       LRS
                1
       RND
                              PERCENTAGE OF INTERIOR SQUARES
       STO
                INTPE,2
TESTY
       CLA
                HUNDR
       SUB
                INTPE,2
                              PERCENTAGE OF INTERIOR SQUARES
        STO
                EXTPE, 2
                              PERCENTAGE OF EXTERIOR SQUARES
TEST
        TIX
                ORIGIN, 2,1
        TRA
                SC19
SC17
        STZ
                INTPE,2
        TRA
                TESTY
ZEROIN CLA
                                     SET INTERIOR AND EXTERIOR
                ZERO
                              PERCENTAGE OF INTERIOR SQUARES
        STO
                INTPE,2
                              PERCENTAGE OF EXTERIOR SQUARES
        STO
                EXTPE, 2
        TRA
                TEST
SC19
       LXA
                RANGE, 2
                              NUMBER OF SQUARE SIZES INTO IR2
                              MINIMUM SQUARE SIZE
       CLA
                WMIN
                              SQUARE SIZE TO BE PRINTED
        STO
                DIMENS
SC21
       CLA
                **,2
        STO
                TFREQ
                                           Figure 10 - Sheet 6
```

```
CLA
                INT.2
                             FREQUENCY OF INTERIOR SQUARES
       STO
                IFREQ
       CLA
                EXT,2
                             FREQUENCY OF EXTERIOR SQUARES
       STO
                EFREQ
       CLA
                EXTPE,2
                             PERCENTAGE OF EXTERIOR SQUARES
       STO
                EPERC
       CLA
                INTPE,2
                             PERCENTAGE OF INTERIOR SQUARES
       STO
                IPERC
       SXA
                SC20,2
SCOTPT CAL
                =6B17
       CALL
                (STH)
       PZE
                FFORM,0,1
FIRST
       LDQ
                REGNC
                                    PRINT REGION NUMBER
       STR
       LDQ
                ROWC
                                    PRINT ROW NUMBER OF
       STR
                                    REGION.
       LDQ
                COLC
                                    PRINT COLUMN NUMBER OF
       STR
                                    REGION.
       LDQ
                DIMENS
                             PRINT SQUARE SIZE
       STR
                             PRINT TOTAL NUMBER OF SQUARES
       LDQ
                TEREQ
       STR
                                    SQUARES.
                             PRINT NUMBER OF EXTERIOR SQUARES
       LDQ
                EFREQ
       STR
                                    SQUARES.
       LDQ
                IFREQ
                             PRINT NUMBER OF INTERIOR SQUARES
       STR
                                    SQUARES.
       LDQ
                EPERC
                             PRINT PERCENTAGE OF EXTERIOR SQUARES
       STR
                                    EXTERNAL SQUARES.
       LDQ
                IPERC
                             PRINT PERCENTAGE OF INTERIOR SQUARES
       STR
                                    INTERNAL SQUARES
       CALL
                (FIL)
       CLA
                TFREQ
       TZE
                FINISH
       CLA
                DIMENS
                             SQUARE SIZE TO BE PRINTED
       ADD
                ONE
       STO
                             SQUARE SIZE TO BE PRINTED
                DIMENS
SC20
       AXT
                **,2
       TIX
                SC21,2,1
                             HAVE ALL SQUARE SIZES BEEN OUTPUTTED
FINISH CAL
                =6B17
       CALL
                (STH)
       PZE
                FORMAT,0,1
       LDQ
                SKIPLI
       STR
       CALL
                (FIL)
SAVE
       AXT
                **,1
       PXA
                , 1
       STO
                LINE
       CLA
                SIXTY1
       SUB
                LINE
                LINE
       STO
       LDQ
                LINE
       MPY
                WMAXP
```

Figure 10 - Sheet 7

```
XCA
        570
                 ADDER
                 ADDER 44
        LXA
                 #+1,4,FRECT
        TXI
                 CLEAR 94
        SXA
        LXA
                 MRANGE 94
                 ZERO
        CLA
                 **94
CLEAR
        STO
        TIX
                 *-2,4,1
        TRA
                 SC11
LAST
        LXA
                 PICWID, 2
                              PICTURE WIDTH INTO IR2
        CLA
                 ZERO
                 **,2
        STO
        TIX
                 *=2,2,1
        TRA
                 SC9B
                 5,(20A6/20A6///)
FORM
        BCI
FHEAD
        BCI
                 5,1
                 5;
        BCI
        BCI
                 5, SQUARE FREQUENCIES
        BCI
                 5, SQUARE PERCENTAGES
HEAD
        BCI
                 5 ,
                     REGION NUMBER ROW COLUMN
        BCI
                 5, SQUARE SIDE LENGTH
        BCI
                 5, TOTAL EXTERIOR INTERIOR
        BCI
                 5, EXTERIOR INTERIOR
FFORM
        BCI
                 9,(1J13,1J6,1J7,1J22,1J17,1J9,1J9,1J15,1J9/)
FORMAT BCI
                 1,(1A6/)
SKIPLI BCI
                 1,
                 6Ò
USAGE
        BSS
RIN
        BSS
                 1
LIN
        355
                 1
INTREV BSS
                 1
NUOIN
        BSS
                 1
REGIO
        BSS
                 1
COLM
        BSS
                 200
SWCH
        BSS
                 1
        BSS
                 1
PRERIN BSS
                 1
WCUR
        BSS
                 1
ROWC
        BSS
                 1
COLC
                 1
        BSS
REGNC
        BSS
                 1
FRECT
                 7200
        BSS
        BSS
                 1
SIZE
        BSS
                 1
INT
        BES
                 120
                               NUMBER OF INTERIOR SQUARES
EXT
        BES
                               NUMBER OF EXTERIOR SQUARES
                 120
                               PERCENTAGE OF INTERIOR SQUARES
INTPE
        BES
                 120
EXTPE
                               PERCENTAGE OF EXTERIOR SQUARES
        BES
                 120
ROW
        BSS
                 60
COL
        BSS
                 6 Ü
PLV
        B$S
                 1
```

```
85$
                50
INTER
RUGTO
      USS
                50
ADDER
       ESS
2680
       DEC
                O
ONE
       DEC
                1
TWO
                2
       DEC
RANGE
                            NUMBER OF SQUARE SIZES
       BSS
                1
MIMW
       DEC
PLC
       DEC
                4125
                            NUMBER OF LINES
MASK1
       OCT
                777700000000
MASKZ
       OCT
                000077770000
MASK3
                000000007777
       OCT
       PZE
CSTOP
                STOP
CVC
       PZE
                VC.
WMAX
       DEC
                120
                            MAXIMUM SQUARE SIZE TO BE CONSIDERED
REGNS DEC
                60
ENDING BSS
                             LENGTH OF LAST GAP IN INTERVAL
                1
PICWID DEC
                120
                             WIDTH OF PICTURE
HUNDR DEC
                100
TWOHUN DEC
                200
MRANGE BSS
                1
DIMENS BSS
                1
TEREO BSS
IFREQ
      BSS
                1
EFREQ
       BSS
IPERC
       BSS
                1
EPERC
       BSS
WIMAX
       ULC
                120
WP
       DEC
                1
                             NUMBER OF PICTURES
LINE
       BSS
                1
WMAXP
       BSS
                1
SIXTY1 DEC
                61
VC
       CLA
                CSTOP
       STA
                VARING
       TRA
                SC9B
NEWPIC CLA
                CVC
       STA
                VARING
       TRA
                NEWPCT
STUP
       CLA
                WP
                             NUMBER OF PICTURES
       SUB
                ONE
                WP
                             NUMBER OF PICTURES
       STO
       TNZ
                NEWPIC
```

4. Application to TIROS pictures and nephanalyses

The RAMP and REST programs have been applied to two types of pictorial material:

- (a) A set of digitized TIROS cloud cover pictures
- (b) A set of outline-map nephanalyses made from TIROS pictures

4.1 TIROS pictures

Arking (1964) and others have demonstrated the possibility of discriminating cloud from noncloud on TIROS pictures with fair reliability by using an appropriate brightness threshold. He has used this approach in a study of percentage cloud cover as a function of season and geographic location. If RAMP is applied to TIROS pictures, a further analysis of the cloud cover becomes possible in terms of numbers and areas of large connected cloud masses (overcast) as well as total area and "piece size spectrum" of broken cloud cover. Application of REST then provides information about the shapes of the connected cloud masses.

For direct cloud picture input to RAMP a magnetic tape was used containing digitized versions of ten pictures transmitted by TIROS V.

Figure 1 is a reproduction of a high-speed chemical printer output of the first picture of this sequence. (The cooperation of Dr. Albert Arking of the NASA Institute for Space Studies, New York, in making this tape available is gratefully acknowledged.)

The format of this tape is as follows. The first record is an identifying Control Record in FORTRAN binary format containing the following words of information:

- (1) FORTRAN control word
- (2) Output tape reel number
- (3) TIROS number
- (4) Integer 1
- (5) Number of frames this sequence
- (6) R/O pass number
- (7) Sequence number
- (8) Same as (5)

The next record is a Sequence-Data Record in FORTRAN binary format containing the following words of information:

- (1) FORTRAN control word
- (2) TIROS number
- (3) R.O. number
- (4) Mode
- (5) Camera
- (6) Sequence position
- (7) Number of sequences
- (8) and (9) Date
- (10) Number of days
- (11), (12), and (13) Time

- (14) Number of frames.
- (15) Usable frames
- (16) ID scheme
- (17) and (18) Latitude and longitude
- (19) Height
- (20) Right ascension
- (21) Declination
- (22), (23), (24) P.P. longitude, latitude and elevation
- (25) Elevation of sub-satellite point
- (26) Nadir angle
- (27) P.S. angle
- (28) Ersatz
- (29) Roll angle
- (30) Time (minutes)
- (31) ID number
- (32) Frame number

Following the Sequence-Data Record are twenty-four 10-line
Gray Level Records in non-FORTRAN binary format. Picture elements
are packed six per computer word, six bits per element. Brightness
levels range from 63 (the brightest) to 0 (the darkest). Each of these
records is 390 words in length. The picture thus consists of 240 lines
of 234 elements each.*

^{*}This is a 1/4 area scale reduction of the data tape format of 480 lines of 468 elements each, as transmitted directly from the TIROS satellite.

Following this is an eight-word End-of-Line Record marking the end of the first frame. Each of the other nine frames on the tape similarly contains a Sequence-Data Record, 24 Gray Level Records, and an End-of-Line Record.

Only one format change was necessary for input of these pictures to RAMP: the 10-line Gray Level Records were broken up into ten records of one line (234 picture elements) each.

RAMP outputs at eight different brightness threshold levels for the TIROS picture of Figure 1 are shown as the left-hand pictures in Figure 11. Element digital values range from 0 (darkest) to 63 (brightest). The thresholds used were 8, 12, 16, 20, 24, 28, 32, and 36. In each example, elements which are brighter (greater in digital value) than the threshold are printed out; elements darker than threshold are left blank. The right-hand pictures in Figure 11 show the same set of pictures "reversed." Elements whose digital values are less than or equal to the brightness threshold are printed out, while elements exceeding the threshold are left blank. The same set of thresholds was used. An advantage of the reversal is that the bright clouds now correctly appear on the printout as white patches against a dark printed background, so that the printout now resembles a "positive" picture.


4.2 Nephanalyses


The application of RAMP and REST to cloud cover maps, or nephanalyses, provides information about the sizes and shapes of the regions which contain single types of cloud cover as defined by the maps.


Figure 11


RAMP Output for a Typical Cloud Picture


at Various Threshold Levels

















FIGURE I SHEET 5







Besides this climatological map analysis application, RAMP and REST have also been used to establish basic parameters for a proposed approach to automatic cloud cover mapping directly from TIROS pictures. This approach involves the analysis of a set of square neighborhoods on a picture and the identification of the cloud cover contained in these neighborhoods. Clearly, the cloud cover regions identified by such a process cannot be smaller than the square neighborhoods which are analyzed.

Conversely, a study of the sizes of squares which will fit into the regions on a cloud cover map provides an upper bound to the neighborhood sizes which can be used if a given proportion of the regions on an average map are to be identified.

The typical maps of Figure 2 were scanned as described in Section 2.2 (Figure 2 illustrates the possibility of putting many pictures on a single digital tape. An upper bound to the number of such pictures is imposed by the requirement that the map lines be wide enough to remain free of gaps after digitizing.) RAMP outputs for two of these maps were shown as Figures 3 and 7; the REST output for one of them, as Figure 8.

References

- Arking, A. Latitudinal Distribution of Cloud Cover from TIROS III Photographs, Science 143, 1964, 569-572
- Dinneen, G. P. Programming Pattern Recognition, <u>Proceedings</u>, 1955 Western Joint Computer Conference, 94-100
- Freeman, H. Techniques for the Digital Computer Analysis of Chain-Encoded Arbitrary Plane Curves, Proceedings, National Electronics Conference 17, 1961, 421-432
- Hodes, L. Machine Processing of Line Drawings, MIT Lincoln Laboratory Report 54 G-0028, 7 March 1961
- Kirsch, R. A. et al Experiments in Processing Pictorial Information with a Digital Computer, <u>Proceedings</u>, 1957 Eastern Joint Computer Conference, 221-229
- Kirsch, R. A. Computer Interpretation of English Text and Picture Patterns, National Bureau of Standards Report 8394, 1 April 1964
- Narasimhan, R. Labeling Schemata and Syntatic Descriptions of Pictures, Information and Control 7, 1964, 151-179
- Sutherland, I. E. Sketchpad: A Man-Machine Graphical Communication System, MIT Lincoln Laboratory Technical Report No. 296, 30 January 1963
- Unger, S. H. A Computer Oriented Toward Spatial Problems, Proceedings of the IRE 46, 1958, 1744-1750